


Set Up IMAP - Samsung® Instinct®

If you would like to learn more about the differences between POP and IMAP, please see the help topic, "[POP vs. IMAP](#)."

To set up an Instinct for IMAP, perform the following steps:

1. On your computer, activate and download your Desktop Connector by signing up at [Sprint's website](#).
2. Once downloaded, start the Desktop Connector.
3. Enter the user name and password that you created during the signup process.
4. Click the **Next** button.
5. Select the **Enable mobile access to mail, calendar, and contacts** check box.
6. Click the **Please select the messaging application used in your corporation** drop-down menu and select **Standard IMAP Server**.
7. Click the **Next** button.
8. Enter the following information:
 - Display Name—Enter your first and last name. This is the name that will appear in the From field of messages you send.
 - E-mail Address—Enter your entire email address (e.g., myname@mydomain.com).
 - Incoming mail IMAP server—Enter the secure server name:
secure.emailsrvr.com
 - IMAP Port—Select the **Use SSL** check box.
 - Use NTLM Authentication—Do not select the check box.
 - Outgoing mail SMTP server— Enter the secure server name:
secure.emailsrvr.com
 - SMTP Port—Select the **Use SSL** check box.
 - Requires Auth—Select the check box.
 - Trash Folder—Leave as Trash.
 - Sent Items Folder—Enter "Sent" in the field.
 - Root Folder Path—Enter "Inbox." in the field.

Note: The Instinct does not support full IMAP folder access.



The image shows a screenshot of the "Desktop Connector" configuration window. The window title is "Desktop Connector" and it contains a form for entering email profile information. The form fields and their values are as follows:

| Field | Value |
|-----------------------------|-------------------------------------|
| Display Name * | My Name |
| E-mail Address * | myname@mydomain.com |
| Incoming mail IMAP server * | secure.emailsrvr.com |
| IMAP Port * | 993 |
| Use SSL | <input checked="" type="checkbox"/> |
| Use NTLM Authentication | <input type="checkbox"/> |
| Outgoing mail SMTP server * | secure.emailsrvr.com |
| SMTP Port * | 465 |
| Use SSL | <input checked="" type="checkbox"/> |
| Outgoing message encoding * | US-ASCII |
| Requires Auth | <input checked="" type="checkbox"/> |
| Auth Settings... | Auth Settings... |
| Trash Folder | Trash |
| Sent Items Folder | Sent |
| Root Folder Path | Inbox. |

At the bottom of the window, there are four buttons: "< Back", "Next >", "Cancel", and "Help".

9. Click the **Next** button.
10. In the **IMAP User Name** field, enter your entire email address (e.g., myname@mydomain.com).
11. In the **IMAP Password** field, enter the password for your email account.
12. Click the **Next** button.
13. Click the **Finish** button.
14. On your Instinct device, navigate to the **Main** page, and tap the **Email** icon.
15. Tap the **Next** button.
16. Tap the **Work** tab.
17. Tap the **Other** tab.
18. Tap the **Yes** tab.
19. Enter the user name and password that you created during the Desktop Connector signup.

20. Tap the **Next** button.
21. Tap the **Next** button.
22. On the tool tip, tap the **OK** button.